

Article ID: 927392 - Last Review: March 20, 2007 - Revision: 3.2

How to use the Bootrec.exe tool in the Windows Recovery Environment to troubleshoot and repair startup issues in Windows Vista

INTRODUCTION

You can use the Bootrec.exe tool in the Windows Recovery Environment (Windows RE) to troubleshoot and repair the following items in Windows Vista:

- A master boot record (MBR)
- A boot sector
- A Boot Configuration Data (BCD) store

Note When you are troubleshooting startup issues by using the Windows RE, you should first try the **Startup Repair** option in the **System Recovery Options** dialog box. If the **Startup Repair** option does not resolve the issue, or if you must troubleshoot more steps manually, use the Bootrec.exe tool.

MORE INFORMATION

To run the Bootrec.exe tool, you must start Windows RE. To do this, follow these steps:

1. Put the Windows Vista installation disc in the disc drive, and then start the computer.
2. Press a key when you are prompted.
3. Select a language, a time, a currency, a keyboard or an input method, and then click **Next**.
4. Click **Repair your computer**.
5. Click the operating system that you want to repair, and then click **Next**.
6. In the **System Recovery Options** dialog box, click **Command Prompt**.
7. Type **Bootrec.exe**, and then press ENTER.

Note To start the computer from the Windows Vista DVD, the computer must be configured to start from the DVD drive. For more information about how to configure the computer to start from the DVD drive, see the documentation that is included with the computer or contact the computer manufacturer.

Bootrec.exe options

The Bootrec.exe tool supports the following options. Use the option that is appropriate for your situation.

Note If rebuilding the BCD does not resolve the startup issue, you can export and delete the BCD, and then run this option again. By doing this, you make sure that the BCD is completely rebuilt. To do this, type the following commands at the Windows RE command prompt:

- **bcdedit /export C:\BCD_Backup**
- **c:**

- **cd boot**
- **attrib bcd -s -h -r**
- **ren c:\boot\bcd bcd.old**
- **bootrec /RebuildBcd**

/FixMbr

The **/FixMbr** option writes a Windows Vista-compatible MBR to the system partition. This option does not overwrite the existing partition table. Use this option when you must resolve MBR corruption issues, or when you have to remove non-standard code from the MBR.

/FixBoot

The **/FixBoot** option writes a new boot sector to the system partition by using a boot sector that is compatible with Windows Vista. Use this option if one of the following conditions is true:

- The boot sector has been replaced with a non-standard Windows Vista boot sector.
- The boot sector is damaged.
- An earlier Windows operating system has been installed after Windows Vista was installed. In this scenario, the computer starts by using Windows NT Loader (NTLDR) instead of Windows Boot Manager (Bootmgr.exe).

/ScanOs

The **/ScanOs** option scans all disks for installations that are compatible with Windows Vista. Additionally, this option displays the entries that are currently not in the BCD store. Use this option when there are Windows Vista installations that the Boot Manager menu does not list.

/RebuildBcd

The **/RebuildBcd** option scans all disks for installations that are compatible with Windows Vista. Additionally, this option lets you select the installations that you want to add to the BCD store. Use this option when you must completely rebuild the BCD.

APPLIES TO

- Windows Vista Ultimate
- Windows Vista Enterprise
- Windows Vista Business
- Windows Vista Home Premium
- Windows Vista Home Basic
- Windows Vista Business 64-bit Edition
- Windows Vista Enterprise 64-bit Edition
- Windows Vista Home Premium 64-bit Edition
- Windows Vista Home Basic 64-bit Edition
- Windows Vista Ultimate 64-bit Edition

Keywords: kbexpertiseadvanced kbhowto kbinfo KB927392



Get Help Now

Contact a support professional by E-mail, Online, or Phone

Help and Support

Microsoft

©2009 Microsoft