

Windows 8 Navigation

Part 2

The Villages Computer Club

Bob Walton

May-03-2013



OVERVIEW

- Navigation device history
- Navigation Windows 8 style
- Charms Bar details
- **SHUTDOWN & RESTART** shortcuts


'Navigation / Input Device' History

- Keyboard
- Keyboard + *Mouse*
- Keyboard + *Touch-pad* + *Stylus*
- Keyboard + *Touch-screen* + *Stylus*

Windows 8 START screen (EDGE-UI)



Windows 8 START screen: Right-side Corners=Charms Bar







Hot-Key: Win + C = Charms Bar









Start

ROBERT
WALTON











MERO.1

 Desktop	 Bing	 Music	 Federal workers brace for furloughs	 42° Mostly Clear 42°/27° Allen Park
 8 Friday Calendar	 Camera	 People	 Photos	
 Games	 SkyDrive	 Mashable - Basketball Player Tweets Apology After Choking...		
 Internet Explorer	 Mail 1	 Store	 70° The Villages Clear 73°/52° Weather	

MS

 Windows Defender	 Windows Update
 Control Panel	 Computer
 Recycle Bin	 Applications
 RESTART	 SHUTDOWN

UTILITIES

 7-Zip File Manager	 Adobe Reader XI
 Auslogics Disk Defrag	 CDBurnerXP
 Glary Utilities	 Google Chrome
 ImgBurn	 Malwarebytes Anti-Malware
 Microsoft Silverlight	 Mozilla Firefox



Search



Share



Start



Devices



Settings

Charms Bar Items

- **1. Search**
- **2. Share**
- **3. Start**
- **4. Devices**
- **5. Settings**

Charms Bar Items

Search

This charm provides easy access to the system-wide search functionality in Windows 8.

It's context-sensitive, so if you tap it from the Start screen or Windows desktop, it will trigger the new Start Search experience, which lets you find apps (and applications), settings, and files on your PC.

But if you access this charm from within an app, you will instead search that app. For example, you can use this to search for e-mail from within the Mail app.

Charms Bar Items

Share

Via this unique charm, you can share what's on-screen with others using another Metro-style app.

Like many of the other charms, including Search, this functionality is tied to a new, low-level capability in Windows 8 called contracts, in this case the Share contract.

And any Metro-style app can implement this contract to send and/ or receive share requests.

Share doesn't work at all from the Start screen (or the desktop) since these interfaces have nothing to share.

To use Share, you need to be using a Metro-style app first.

Charms Bar Items

Devices

Like most charms, Devices is also context-sensitive, so what you see here will be determined by two things: which compatible devices are attached to (or included in) your PC or device and what you're doing at the time.

The Device charm is most often used to access a printer or, for those with two or more screens, to determine how the secondary screens are used.

Charms Bar Items

Settings

Another context-sensitive charm, Settings provides an interesting array of features.

At the top of the Settings pane that appears are links to settings that pertain to the current view, which could be the Start screen, a Metro-style app, or the desktop environment.

But at the bottom, you will find links to settings that are always available, from any of those experiences.

Hot-Key: Win + I = Settings

Start

MERO.1

A grid of Windows Start screen tiles for user MERO.1. The tiles include: Desktop (flowers), Trending (Man kills TV ho... Rick Springfield Capriati), Music (headphones), Before the conclave, horse-trading has begun, Allen Park (59° Cloudy 59°/45°), Calendar (10 Sunday), Camera, People, Photos, Games (game controller), SkyDrive, ABC News - Fighting at 48: Bernard Hopkins Becomes Oldes..., Internet Explorer, Mail, Store, Rio de Janeiro, Brazil, Maps, Messaging, Video, and Weather (74° The Villages Clear 80°/55°).

MS

A grid of Windows Start screen tiles for user MS. The tiles include: Windows Defender, Windows Update, Control Panel, Computer, Recycle Bin, Applications, RESTART, and SHUTDOWN.

Settings

Start

Tiles

Help

Context Sensitive

System tray icons including Network, Volume (13), Unavailable, Notifications, Power, and Keyboard.

Change PC settings

Hot-Key: Win + I = Settings

Start


MERO.1



Start screen tiles for user MERO.1:

- Desktop
- Trending: Man kills TV ho... Rick Springfield Capriati
- Music
- Before the conclave, horse-trading has begun
- 59° Cloudy 59°/45° Allen Park
- Calendar: 10 Sunday
- Camera
- People
- Photos
- Games
- SkyDrive
- ABC News - Fighting at 48: Bernard Hopkins Becomes Oldes...
- Internet Explorer
- Mail
- Store
- Rio de Janeiro, Brazil
- Maps
- Messaging
- Video
- 74° The Villages Clear 80°/55° Weather

MS



Start screen tiles for user MS:

- Windows Defender
- Windows Update
- Control Panel
- Computer
- Recycle Bin
- Applications
- RESTART
- SHUTDOWN

Settings

Start

Tiles

Help

Always Available



Always Available system tray icons:

- Network
- 13
- Unavailable
- Notifications
- Power
- Keyboard

Change PC settings

Charms Bar Items: SETTINGS



Charms Bar Items: SETTINGS

Where ever you open the Settings Charm you will notice that the bottom half never changes, these are system wide settings and give you access to:

Network - where you can configure your internet connection

Volume - Where you can adjust the master volume between 0 and 100 percent


Brightness - Letting you adjust the brightness of your screen

Notifications - Giving you the option to suspend notifications for different periods of time


Power - Allowing you to shut down your computer/tablet

Keyboard - Lets you change your keyboard language.

Left-side, Upper or Lower corner = Open apps



Hot-Key: Win + Tab = Open Apps



Hot-Key: Win + X = PowerUser Menu


Start

ROBERT WALTON 


MERO.1

MS


UTILITIES




Desktop
Trending
Chris Brown
North Korea
Bin Laden son-...
Bing
Music
42°
Mostly Clear
42°/27°
Allen Park
Friday
Calendar
Camera
People
Photos
SkyDrive
Ferrari \$1.3M
Hybrid Hits
Resurgent
Luxury Marke
Mail 1
Store
Prague, Czech Republic
Messaging
Video
70°
The Villages
Clear
73°/52°
Weather



Windows Defender
Windows Update
Control Panel
Computer
Recycle Bin
Applications
RESTART
SHUTDOWN



7-Zip File Manager
Adobe Reader XI
Mozilla Thunderbird
Auslogics Disk Defrag
CDBurnerXP
LibreOffice
Glary Utilities
Google Chrome
LibreOffice
ImgBurn
Malwarebytes Anti-Malware
LibreOffice
Microsoft Silverlight
Mozilla Firefox
Picasa 3



- Programs and Features
- Power Options
- Event Viewer
- System
- Device Manager
- Disk Management
- Computer Management
- Command Prompt
- Command Prompt (Admin)
- Task Manager
- Control Panel
- File Explorer
- Search
- Run
- Desktop

Hot-Key: Win + C & Win + X = PowerUser Menu



Hot-Key: Win + I = Settings/Power

Start

MERO.1

A grid of Windows Start screen tiles for user MERO.1. The tiles include: Desktop (flowers), Trending (news), Music (headphones), Afghan president: US and Taliban are colluding (news), 59° Mostly Cloudy 59°/45° (weather), Allen Park (weather), Calendar (10 Sunday), Camera (camera icon), People (two people icon), Photos (photo gallery), DOW 14,397.07 +0.47% 4:37 PM EST (stock market), Games (game controller icon), SkyDrive (cloud icon), ESPN - Amar'e Stoudemire to miss 6 weeks (sports), Rio de Janeiro, Brazil (location), Internet Explorer (IE icon), Mail (envelope icon), Store (Windows Store icon), 74° The Villages Clear 80°/55° (weather), Maps (map icon), Messaging (speech bubble icon), Video (video player icon), and Weather (weather icon).

MS

A grid of Windows Start screen tiles for user MS. The tiles include: Windows Defender (shield icon), Windows Update (update icon), Control Panel (gear icon), Computer (desktop icon), Recycle Bin (trash can icon), Applications (folder icon), RESTART (play button icon), and SHUTDOWN (stop sign icon).

Settings

Start


Tiles

Help

A screenshot of the Windows Settings application. The 'Power' option is highlighted with a red box. The menu includes: Sleep, Shut down, Restart, and Power. Other settings like Network, Inavailable, Notifications, and Keyboard are visible in the background.

Change PC settings

Desktop shortcuts: SHUTDOWN & RESTART




Desktop: Create a SHORTCUT

1. Right-Click

2. Left-Click

3. Left-Click



Commands: Shutdown & Restart


System **SHUTDOWN**

SHUTDOWN /S /T 003


System **RESTART**

SHUTDOWN /R /T 003


Desktop: Create a SHUTDOWN shortcut



Desktop: Create a SHORTCUT



Desktop shortcut: Change icon



Desktop shortcut : Change icon

The image shows a Windows 8 desktop with a blue background. A desktop shortcut named 'SHUTDOWN' is visible. A red callout box with the number '1' and an arrow points to the shortcut, with the text '1. Right-Click, select PROPERTIES'. Below the desktop, the 'Change Icon' dialog box is open. A red callout box with the number '2' and an arrow points to the 'Change Icon...' button in the 'SHUTDOWN' properties window. Another red callout box with the number '3' and an arrow points to a red power button icon in the 'Change Icon' dialog's list. A red callout box with the number '4' and an arrow points to the 'OK' button in the 'Change Icon' dialog. A red callout box with the number '5' and an arrow points to the 'Apply' button in the 'SHUTDOWN' properties window. A final red callout box with the number '6' and an arrow points to the 'OK' button in the 'SHUTDOWN' properties window.

1. Right-Click, select PROPERTIES

2


3

4


5

6

Desktop: Create a RESTART Shortcut



Desktop: Create a RESTART Shortcut




START Screen: SHUTDOWN & RESTART

Start

RJW 

METRO.1




The METRO.1 Start screen features a grid of tiles. The top row includes Desktop, a clock showing 1:06 PM on Thu, 4/25/2013, Games, Internet Explorer, SkyDrive, and a photo of a basketball player. The second row shows Weather (78° in The Villages), Allen Park weather (49°), Mail, Messaging, Store, and a photo of a stadium. The third row contains Bing, Calendar (25 Thursday), Music, a news tile about Syria, a RESTART tile, and a SHUTDOWN tile. The bottom row includes Camera, a news tile about Exxon, People, and Photos. A red rectangle highlights the RESTART and SHUTDOWN tiles.

METRO.2




The METRO.2 Start screen features a grid of tiles. The top row includes Getting Started with Windows 8, Cheat Keys & Tips, Windows 8 Shortcuts, Windows 8 Shortcuts, and Tile A File. The second row contains NINITE1, NINITE.IE10, and ICONTEST.

MS.1



The MS.1 Start screen features a grid of tiles. The top row includes Windows Defender, Control Panel, and Recycle Bin. The bottom row includes Hyper-V Virtual Machine...

Pin to START SCREEN & TASKBAR



Win8 Navigation Links

1. Getting Started with Windows 8 (Win8 app) [HP]

<http://apps.microsoft.com/webpdp/en-us/app/getting-started-with-windows-8/c0676a60-7275-4198-8a6c-c8ba884457e0>

2. Windows 8 Tutorial [ACER]

<http://www.acer.com/windows8-tutorial/template.html>

3. Toshiba How-To: Getting started with Windows 8 [TOSHIBA]

<https://www.youtube.com/watch?v=dusDA1zKJoE>

4. Maximize your first 30 minutes with Windows 8

<https://www.pcworld.com/article/2013138/maximize-your-first-30-minutes-with-windows-8.html>

5. Lynda.com (Windows 8 Essential Training)

<http://www.lynda.com/Windows-tutorials/Windows-8-Essential-Training/84572-2.html>

6. GCFLearnfree.org (Windows 8)

<http://www.gcflearnfree.org/windows8>

7. Classic Start

<https://ninite.com/>

8. The Villages Computer Club – Self Help – Windows 8

<http://thevillagescomputerclub.com/windows8.php>

Thank You!

... Questions?

