

## EASY CD CREATOR 5 PLATINUM

1. Open Roxio. The Select a Project window will open.
  2. Select one of the 4 buttons: Make a music CD, Make a Data CD, Make a Photo or Video CD or Disk Copier.
  3. Click Sound Stream (if making a music cd). There will be 2 windows: the right is to select source. The left is select destination.
  4. On each side are 3 icons.
  5. Select Music CD as source, Select music Library as source or select Folder as source.
  6. The same icons appear on the select destination side.
  7. Put a music CD in the CD Player/writer. Click on the CD in the Select Source.
  8. It will test the speed of the read/write drive. After the test, tracks will appear in the source box.
  9. Select some or all of the tracks. The selected tracks will appear in the Destination box.
  10. Select a destination such as the CD icon. Instructions will appear to Save or Record.
- If you have a combo drive, that is one drive that plays or writes, then you should select a Folder on your hard drive and copy the selections to that folder. From the folder you can copy to the blank CD.

You can also choose the Music Project to make a CD in mp3 format.

To make a DATA CD, the Direct CD will allow you to format the CD so you can use Windows to drag and drop files onto the CD. This allows you to use the CD as a floppy disk, or as a flash drive. You can get 700-750 Megabytes on each cd. This equals 750 floppy disks.

The button DATA DVD will make a DVD if your writer is a DVD Writer. A DVD will store about 4.7gigs, equal to 4,700 floppy disks.

Button 3C has 4 buttons. Select Photo Album and click on photo album...go to album and click Open.

Click on Add Image and select floppy, flash drive or wherever your images are stored.

Click on an image and click OPEN. They will appear in a box in the Photo album.

When you're finished selecting, click SAVE. Give the album a name.

Go to any of the icons at the top of the window and use one of those items. The Post Card needs a video saved as a media. Video impressions and video relates to a video which can be made using single images.

Button 3D is to make a diskcopy of a CD.

Click on disk copier and you get 2 choices: copy from and record to. IF you have two separate drives you can copy a CD directly from the reader to the writer.

Revised 6/22/2009 JMM